



Vendor: HP

Exam Code: HP0-P10

Exam Name: HP Integrity Server Multi-OS Installation &
Deployment

Version: DEMO

QUESTION 1

From the EFI Boot Manager, how can you get information about the installed memory DIMMs?

- A. Go to the EFI Shell and enter: info mem
- B. It is not possible to get the information offline.
- C. The information displays automatically at the EFI Boot Manager menu.
- D. Go to the System Configuration menu and choose Memory Configuration.

Answer: A

QUESTION 2

What does an amber blinking System LED on an Integrity rx2620 indicate?

- A. System is in error state
- B. Remote access is enabled
- C. A system warning
- D. Management Processor is powered off

Answer: C

QUESTION 3

The rx3600 and rx6600 have LEDs which show the FRU Health status. How can you view the state of these LEDs remotely?

- A. From the MP main menu, select VFP
- B. From the MP main menu, select SL
- C. From the MP main menu, select CM, then LS
- D. From the MP main menu, select CM, then DF

Answer: A

QUESTION 4

Where is the diagnostic panel on an Integrity rx4640 server located?

- A. top
- B. front
- C. back
- D. left side
- E. right side

Answer: A

QUESTION 5

Where does HP OpenVMS store all error information?

- A. /var/adm/syslog/syslog.log
- B. SYS\$ERRLOG:SYSTEM.LOG
- C. SYS\$ERRORLOG:ERRLOG.SYS

D. SYS\$MANAGER:OPERATOR.LOG

Answer: C

QUESTION 6

The diagnostic panel on an Integrity rx4640 shows a fan failure. What information on the Management Processor (MP) shows you when the fan failed?

- A. MP:CM> PS
- B. MP:CM> SS
- C. MP> SL --> L - Live Events
- D. MP> SL --> E - System Event

Answer: D

QUESTION 7

You just installed an Integrity rx2620 server. How do you set the MP and system times?

- A. Use the MP date command to set time and date.
- B. The time will be set automatically during system boot.
- C. Use the EFI shell command time to set time and date of the MP.
- D. Use the MP date command to set the date, and use the MP time command to set the time.

Answer: C

QUESTION 8

Which Offline Diagnostics Environment (ODE) utility should you use to test processors on an Integrity server?

- A. WDIAG
- B. IA64DIAG
- C. CPUDIAG
- D. PROCDIAG

Answer: C

QUESTION 9

How can you determine the firmware version that is running on an HP Integrity system? (Select two.)

- A. At the EFI Boot Manager menu, open the EFI shell and enter info fw.
- B. At the MP main menu, open the Command Menu (cm) and enter firmware.
- C. At the EFI Boot Manager menu, go to the Firmware menu and select Version.
- D. At the EFI Boot Manager menu, go to the Firmware Configuration menu and select Version.
- E. If you access the EFI Boot Manager menu using iLO, the firmware versions display automatically.

Answer: AE

QUESTION 10

How can you access the UUID on an entry-level HP Integrity server? (Select two.)

- A. The UUID is written on the system information label of the server.
- B. At the EFI Boot Manager menu, access the EFI Shell; then enter info sys.
- C. At the Management Processor (MP) main menu, go to the Command Menu and enter id.
- D. At the EFI Boot Manager menu, access the System Configuration menu and select System UUID.
- E. If you access the EFI Boot Manager menu using integrated Lights-Out (iLO), the UUID displays automatically.

Answer: AB

QUESTION 11

What is the difference between a Machine Check Abort (MCA) and a Transfer of Control (TOC)?

- A. An MCA is a software dump; a TOC is a hardware register dump.
- B. An MCA is a hardware register dump; a TOC initiates a software dump.
- C. An MCA dump is for Windows systems; a TOC is for HP-UX systems.
- D. An MCA dump is for HP-UX systems; a TOC is for Windows systems.

Answer: B

QUESTION 12

Which Offline Diagnostics Environment (ODE) utility should you use to test the memory of an Integrity server?

- A. MAPPER
- B. SYSDIAG
- C. MEMDIAG
- D. DIMMDIAG

Answer: C

QUESTION 13

Which front panel LEDs on an Integrity rx2620 can indicate an error?

- A. Locator LED and System LED
- B. Power LED and Diagnostic LEDs
- C. System LED and Diagnostic LEDs
- D. Diagnostic LEDs and Locator LED

Answer: C

Thank You for Trying Our Product

PassLeader Certification Exam Features:

- ★ More than **99,900** Satisfied Customers Worldwide.
- ★ Average **99.9%** Success Rate.
- ★ **Free Update** to match latest and real exam scenarios.
- ★ **Instant Download** Access! No Setup required.
- ★ Questions & Answers are downloadable in **PDF** format and **VCE** test engine format.
- ★ Multi-Platform capabilities - **Windows, Laptop, Mac, Android, iPhone, iPod, iPad.**
- ★ **100%** Guaranteed Success or **100%** Money Back Guarantee.
- ★ **Fast**, helpful support **24x7**.



View list of all certification exams: <http://www.passleader.com/all-products.html>



Microsoft



ORACLE



CITRIX



JUNIPER
NETWORKS



EMC²
where information lives[®]

10% Discount Coupon Code: STNAR2014