

Exam Code: 920-355

Exam Name: BCS 3000 Rls. 1.0 Storage Networking OAM

Vendor: Nortel

Version: DEMO

Part: A

1: What are the different user account levels in BCS Director?

- A.root, admin, user
- B.root, admin, operator
- C.admin, operator, user
- D.admin, operator, observer

Correct Answers: D

2: In the Command Line Interface (CLI), which command turns off the power on the DSM in slot 1?

- A.power off slot 1
- B.configure slot power 1 off
- C.configure power slot 1 off
- D.configure power off slot 1

Correct Answers: B

3: Which two CLI commands can be used to retrieve performance monitoring information? (Choose two)?

- A.show stats
- B.show stats all
- C.show dnm <slot> stats
- D.show stats dnm <slot> <port> [stat-string]

Correct Answers: B D

4: In the Command Line Interface (CLI), which command will let you change the internal IP address range of the BCS 3000 shelf?

- A.configure ip ip-prefix <ip-address>
- B.configure node ip-prefix <ip-address>
- C.configure port ip-prefix <ip-address>
- D.configure shelf ip-prefix <ip-address>

Correct Answers: B

5: What CLI command would you use to set the protocol for a client port?

- A.configure profile <slot> <port> <protocol>
- B.configure slot <slot> port <port> protocol <protocol>
- C.configure port protocol <protocol> dnm <slot> <port>
- D.configure protocol <protocol> dnm <slot> port <port>

Correct Answers: C

6: In the Command Line Interface (CLI), what are the different alarm severity ratings from lowest to highest?

- A.alert, event, major, critical
- B.event, minor, major, critical

- C.warning, alert, major, critical
- D.warning, minor, major, critical

Correct Answers: D

7: Which troubleshooting capability is supported on the DNM?

- A.Traffic sniffer
- B.Port loopback
- C.Port mirroring
- D.Traffic generation

Correct Answers: B

8: What two of the following authentication options can be configured on the BCS 3000? (Choose two.)

- A.LDAP
- B.Active Directory
- C.Centralized authentication (RADIUS)
- D.Local challenge/response authentication

Correct Answers: C D

9: Which two parameters can be provisioned for a GigE port? (Choose two.)

- A.Holdoff timer
- B.Duplex mode
- C.Auto-negotiation
- D.Buffer-to-buffer credit override

Correct Answers: A C

10: How would you reprovision a replaced Dynamic Network Module (DNM)?

- A.Rebuild profile via CLI
- B.Re-apply active DNM profile
- C.Restore configuration from backup file
- D.Nothing - DNM auto-provisions immediately

Correct Answers: D