

Exam Code: 920-544

Exam Name: Carrier VoIP Integrated Element Mgmt
System (IEMS) Ops

Vendor: Nortel

Version: DEMO

Part: A

1: Which feature is part of the alarm count panel?

- A.Alarms with a warning severity are not shown.
- B.A summary of all critical alarms may be obtained.
- C.An annotation may be made from the alarms count panel.
- D.Alarms may be acknowledged from the alarms counts panel.

Correct Answers: B

2: Under which of the following in the topology tree is the Alarms node found?

- A.Inventory
- B.Performance
- C.Network Events
- D.Fault Management

Correct Answers: D

3: Which action may be used to display the icon of the managed object that is the source of a given alarm?

- A.From the alarm popup menu, select Show Map.
- B.Double-click on the alarm and select Show Map Detail.
- C.From the alarm popup menu, select Show Managed Object.
- D.Double-click on the alarm and select Managed Object Detail.

Correct Answers: A

4: Which of the following is true for events that are received from devices that are not part of Integrated EMS inventory database?

- A.The IEMS will temporarily add the source device to the inventory.
- B.These events have a source field value of Unrecognized Device.
- C.The IEMS application assigns these events a logkey value of IEMS601.
- D.The IEMS application will propagate these events to alarms with a minor severity.

Correct Answers: C

5: Which protocol is used to establish an Operator Client session from the IEMS into the Multi-service Data Manager?

- A.SSH
- B.Telnet
- C.HTTPS
- D.SNMPv3

Correct Answers: C

6: Which Network Element requires its GUI element manager application to be installed on the client?

- A.STORM
- B.Call Agent

C.ERS 8600

D.MSS 15000

Correct Answers: C

7: Which statement is true for performing IEMS application upgrades in a dual server (HA) environment?

A.During the upgrade, neither server is in service.

B.The upgrade must first be performed on the active server.

C.A failover must not be performed until both servers are upgraded.

D.Updates are performed on the standby server, while the active server is in service.

Correct Answers: D

8: How many simultaneous sessions of each of the four supported Northbound fault streams are supported?

A.2

B.4

C.6

D.8

Correct Answers: C

9: Which two must be provisioned on the IEMS in order to set up a Northbound SNMP fault stream? (Choose two.)

A.the directory of the SNMP trap destination host (Managerdir)

B.the MAC address of the SNMP trap destination (Managemac)

C.the IP address of the SNMP trap destination host (Managerhost)

D.the port number of the SNMP trap destination host (Managerport)

Correct Answers: C D

10: Which Servman command can be issued to start the IEMS server application?

A.start IEMS

B.servstart IEMS

C.startserv IEMS

D.servman start IEMS

Correct Answers: B